

Barbie-Schreibmaschine Modell E117BA - Britisches Tataturlayout
Substitutionstabellen der 4 Alphabete

Chr	C1	C2	C3	C4
a	i	t	h	s
b	c	o	r	n
c	o	r	n	e
d	l	b	c	o
e	a	i	t	h
f	p	u	q	k
g	x	d	l	b
h	s	f	p	u
i	t	h	s	f
j	v	g	x	d
k	y	z	w	;
l	b	c	o	r
m	j	v	g	x
n	e	a	i	t
o	r	n	e	a
p	u	q	k	y
q	k	y	z	w
r	n	e	a	i
s	f	p	u	q
t	h	s	f	p
u	q	k	y	z
v	g	x	d	l
w	;	ç	+	%
x	d	l	b	c
y	z	w	;	ç
z	w	;	ç	+

Chr	C1	C2	C3	C4
A	>	R	S	E
B	F	C	A	>
C	A	>	R	S
D	U	G	Y	P
E	T	H	O	N
F	C	A	>	R
G	Y	P	Q	K
H	O	N	I	L
I	L	D	U	G
J	V	<	X	1
K	J	V	<	X
L	D	U	G	Y
M	Z	B	F	C
N	I	L	D	U
O	N	I	L	D
P	Q	K	J	V
Q	K	J	V	<
R	S	E	T	H
S	E	T	H	O
T	H	O	N	I
U	G	Y	P	Q
V	<	X	1	2
W	.	M	Z	B
X	1	2	3	4
Y	P	Q	K	J
Z	B	F	C	A

Chr	C1	C2	C3	C4
0	5	6	7	8
1	2	3	4	0
2	3	4	0	5
3	4	0	5	6
4	0	5	6	7
5	6	7	8	9
6	7	8	9	-
7	8	9	-	..
8	9	-	..	\$
9	-	..	\$	£

Chr	C1	C2	C3	C4
-	..	\$	£	€
'	_	)	(	*
!	&	"	m	j
"	m	j	v	g
#	@	?	/	^
%	:	,	W	.
&	"	m	j	v
(	*	#	@	?
)	(	*	#	@
*	#	@	?	/
,	W	.	M	Z
.	N	Z	B	F
..	\$	£	€	=
/	^	!	&	"
:	,	W	.	N
;	ç	+	%	:
?	/	^	!	&
@	?	/	^	!
^	!	&	"	m
_	)	(	*	#
+	%	:	,	W
<	X	1	2	3
=	'	_	)	(
>	R	S	E	T
ç	+	%	:	,
£	€	=	'	_
\$	£	€	=	'
€	=	'	_	)